


You now have your personal access token for authenticating with the Graniitti API. The token will expire in 356 days.

Recreating your personal access token

If you forget your personal access token, or if you need a new one for some other reason, you can recreate the token.

 Recreating the token renders your current token invalid. If you have applications that use the current token, their Graniitti API requests will no longer work after you recreate the token.

To recreate your personal access token:

1. In the Control Panel, select **Utilities > Frosmo APIs**.
2. In the **Graniitti API** section, click **Recreate token**.

Your personal access token

All requests to the Graniitti API must be authenticated with an **access token**. Requests that are not authenticated always fail.

You can **create your personal access token** below. Use the same token in all your applications that call the Graniitti API. If you forget the token, you can **recreate** it, but note that the previous token will no longer be valid. You can also **revoke** your current token.

To authenticate a Graniitti API request, add your token to the request using the **Authorization** header. The value of the header is "Bearer" followed by a space and then the token.

```
Authorization: Bearer <your personal access token>
```

Recreate token **Revoke token**


Token exists and expires on 2021-05-13 10:00:00.

3. Copy the token. It will not be shown on the page again.

You have recreated your personal access token. Use the new token in place of the old one in all Graniitti API requests. The new token will expire in 356 days.

Revoking your personal access token

If you no longer need your personal access token, you can revoke it.

 Revoking the token renders it invalid. If you have applications that use the token, their Graniitti API requests will no longer work after you revoke the token.

To revoke your personal access token:

1. In the Control Panel, select **Utilities > Frosmo APIs**.
2. In the **Graniitti API** section, click **Revoke token**.

Your personal access token

All requests to the Graniitti API must be authenticated with an **access token**. Requests that are not authenticated always fail.

You can **create your personal access token** below. Use the same token in all your applications that call the Graniitti API. If you forget the token, you can **recreate** it, but note that the previous token will no longer be valid. You can also **revoke** your current token.

To authenticate a Graniitti API request, add your token to the request using the **Authorization** header. The value of the header is "Bearer" followed by a space and then the token.

```
Authorization: Bearer <your personal access token>
```

[Recreate token](#)

[Revoke token](#)

Token exists and expires on 2021-05-13 10:00:00.

You have revoked your personal access token and can no longer use it to authenticate Graniitti API requests.