

Graniitti API authentication

All requests to the Graniitti API must be authenticated. The API uses token-based authentication over HTTPS. Requests that are not authenticated or that are sent over plain HTTP always fail.

- [Authenticating a request](#)
- [Getting your personal access token](#)
- [Recreating your personal access token](#)
- [Revoking your personal access token](#)

Authenticating a request

To authenticate a request, add your personal access token to the request using the `Authorization` header, and prefix the token with "Bearer" followed by a space, as shown in the following example.

```
curl -X GET \  
--header 'Authorization: Bearer <access_token>' \  
'https://<graniitti_api_domain>/v0/users'
```

If you do not already have a token, [get it from the Frosmo Control Panel](#). You can also [recreate](#) or [revoke](#) an existing token. The token is valid for 356 days from the moment of creation.



Do not make Graniitti API requests in client-side code that is accessible to parties you do not trust, as this will expose your token to them. Use the Graniitti API only in server-side code and in client-side code that is only accessible to parties you trust.

Getting your personal access token

To get your personal access token:

1. In the Frosmo Control Panel, in the header, click your username, and select **API Access**.
2. In the **Graniitti API** section, click **Create token**.

Your personal access token

All requests to the Graniitti API must be authenticated with an **access token**. Requests that are not authenticated always fail.

You can **create your personal access token** below. Use the same token in all your applications that call the Graniitti API. If you forget the token, you can **recreate** it, but note that the previous token will no longer be valid. You can also **revoke** your current token.

To authenticate a Graniitti API request, add your token to the request using the **Authorization** header. The value of the header is "Bearer" followed by a space and then the token.

```
Authorization: Bearer <your personal access token>
```

Create token

3. Copy the token. It will not be shown on the page again.

Recreate token Revoke token

Token exists and expires on 2021-05-13 10:00:00.

⚠ Copy the access token. It will not be shown on this page again.

```

eyJhbGciOiJSUzI1NiIsInR5cCI6IkpXVCIsImp0aSI6ImNvbmdyYXR1bGF0aW9uc29uZmluZGlu
Z3RoZXN1bGkiOiJjb25ncmF0dWxhdGlbnNvbmdmZpbmRpbmd0aGlzliwic3ViIjoiaMTIz
NDU2Nzg5MCIsm5iZiI6MTUxNjIzOTAyMiwiZXhwIjoxNTE2MjM5MDIyLCJpYXQiOiE1MTYyMz
kwMjJ9.CdafCPts0fmooD7nmASMuTpt2H_gLSLJy7xzipVJiKuxQKAHPB5vk-
1s30H6lx4bchOJx_UOd2RyQI7A8D9opa6cQYgJA8tV2JC1Ay1wflMzZsNjICDI8Qs0J4CQdKIV1
RE9OM0J4OGet0y8b5h5_69NSLQUHWG-D0ceGOXDusshQbzyg0-9wMPehTWC-
xoL8uwH7ofX9spaU6rW_3mt0GbSrYOjUfNbzNmZNBVrRkt9j4WiH7uyhWPsRltjECSzUAlJUg
KBvZyWrdECZll_CRo2StHvp34COKBglI0Foijtj-g4XTPJw47GvNquMXo-
YhcgzcMUDehr9RG5g42KUgw

```

You now have your personal access token for authenticating with the Graniitti API. The token will expire in 356 days.

Recreating your personal access token

If you forget your personal access token, or if you need a new one for some other reason, you can recreate the token.

⚠ Recreating the token renders your current token invalid. If you have applications that use the current token, their Graniitti API requests will no longer work after you recreate the token.

To recreate your personal access token:

1. In the Frosmo Control Panel, in the header, click your username, and select **API Access**.
2. In the **Graniitti API** section, click **Recreate token**.

Your personal access token

All requests to the Graniitti API must be authenticated with an **access token**. Requests that are not authenticated always fail.

You can **create your personal access token** below. Use the same token in all your applications that call the Graniitti API. If you forget the token, you can **recreate** it, but note that the previous token will no longer be valid. You can also **revoke** your current token.

To authenticate a Graniitti API request, add your token to the request using the **Authorization** header. The value of the header is "Bearer" followed by a space and then the token.

```
Authorization: Bearer <your personal access token>
```

Recreate token Revoke token

Token exists and expires on 2021-05-13 10:00:00.

3. Copy the token. It will not be shown on the page again.

You have recreated your personal access token. Use the new token in place of the old one in all Graniitti API requests. The new token will expire in 356 days.

Revoking your personal access token

If you no longer need your personal access token, you can revoke it.

⚠ Revoking the token renders it invalid. If you have applications that use the token, their Graniitti API requests will no longer work after you revoke the token.

To revoke your personal access token:

1. In the Frosmo Control Panel, in the header, click your username, and select **API Access**.
2. In the **Graniitti API** section, click **Revoke token**.

Your personal access token

All requests to the Graniitti API must be authenticated with an **access token**. Requests that are not authenticated always fail.

You can **create your personal access token** below. Use the same token in all your applications that call the Graniitti API. If you forget the token, you can **recreate** it, but note that the previous token will no longer be valid. You can also **revoke** your current token.

To authenticate a Graniitti API request, add your token to the request using the **Authorization** header. The value of the header is "Bearer" followed by a space and then the token.

```
Authorization: Bearer <your personal access token>
```

[Recreate token](#) [Revoke token](#)

Token exists and expires on 2021-05-13 10:00:00.

You have revoked your personal access token and can no longer use it to authenticate Graniitti API requests.